

Aimetis Symphony Mobile

(Mobile Bridge and/or Mobile Applications)

2.2.0 - 2.6.x

Disclaimers and Legal Information

Copyright © 2015-2020 Aimetis Inc. All rights reserved.

This material is for informational purposes only. AIMETIS MAKES NO WARRANTIES, EXPRESS, IMPLIED OR STATUTORY, AS TO THE INFORMATION IN THIS DOCUMENT.

Complying with all applicable copyright laws is the responsibility of the user. Without limiting the rights under copyright, no part of this document may be reproduced, stored in or introduced into a retrieval system, or transmitted in any form or by any means (electronic, mechanical, photocopying, recording, or otherwise), or for any purpose, without the express written permission of Aimetis Corp.

Aimetis may have patents, patent applications, trademarks, copyrights, or other intellectual property rights covering subject matter in this document. Except as expressly provided in any written license agreement from Aimetis, the furnishing of this document does not give you any license to these patents, trademarks, copyrights, or other intellectual property.

Aimetis and Aimetis Symphony are either registered trademarks or trademarks of Aimetis Corp. in the United States and/or other countries.

Document History

Date	Description
August 2020	Mobile Bridge 2.6.0.8
April 2018	Mobile Bridge 2.6.0.7 (private release)
September 2017	Mobile Bridge 2.6.0.6
July 2017	Mobile Bridge 2.6.0.5
May 2017	Mobile Bridge 2.6.0.4 (private release)
February 2017	Mobile Bridge 2.6.0.3 (private release)
February 2017	Mobile Bridge 2.6.0.2
February 2017	Mobile Bridge 2.6.0.1
November 2016	Mobile Bridge 2.6
November 2016	Mobile Bridge 2.2.4
July 2016	Mobile Bridge 2.2.3
May 2016	Mobile Bridge 2.2.2
January 2016	Mobile Bridge 2.2.1
November 2015	Mobile Bridge 2.2.1 iOS application
November 2015	Known Issue added to Mobile Bridge 2.2.0 for Windows Server 2003 and Windows XP
October 2015	Mobile Bridge 2.2.0

Release 2.6.0.8

Note: To install Symphony Mobile Bridge 2.6.0.8 on an Aimetis Physical Security Appliance, the Physical Security Appliance must have at least 16GB of storage for the operating system (SATA DOM).

Note: Symphony Mobile Bridge 2.6.0.8 does not support Windows XP or Windows Server 2003.

Mobile Bridge

Fixes	
VMS-1912	The Symphony Mobile Bridge connects to the Symphony Server as expected after applying the cumulative update for .NET (KB4565627 or KB4565633) from Microsoft.

Release 2.6.0.7

Note: To install Symphony Mobile Bridge 2.6.0.7 on an Aimetis Physical Security Appliance, the Physical Security Appliance must have at least 16GB of storage for the operating system (SATA DOM).

Note: Symphony Mobile Bridge 2.6.0.7 does not support Windows XP or Windows Server 2003.

Mobile Bridge

Fixes	
VMS-1620	The filepath for the server logs is correct when you install Mobile Bridge on a computer without Symphony Server.
VMS-1644	Mobile Bridge does not use impersonation IDs to authenticate with the Symphony Server.

Release 2.6.0.6

Note: To install Symphony Mobile Bridge 2.6.0.6 on an Aimetis Physical Security Appliance, the Physical Security Appliance must have at least 16GB of storage for the operating system (SATA DOM).

Note: Symphony Mobile Bridge 2.6.0.6 does not support Windows XP or Windows Server 2003.

Mobile Bridge

Fixes	
VMS-1501	The Mobile Bridge is retrieving historical video as expected.

Release 2.6.0.5

This release includes new features, improvements, and fixes from previous private releases.

Note: To install Symphony Mobile Bridge 2.6.0.5 on an Aimetis Physical Security Appliance, the Physical Security Appliance must have at least 16GB of storage for the operating system (SATA DOM).

Note: Symphony Mobile Bridge 2.6.0.5 does not support Windows XP or Windows Server 2003.

Mobile Bridge

Fixes	
VMS-1491	Alarms appear as expected in the Mobile Bridge SDK sample.

Release 2.6.0.4

Note: To install Symphony Mobile Bridge 2.6.0.4 on an Aimetis Physical Security Appliance, the Physical Security Appliance must have at least 16GB of storage for the operating system (SATA DOM).

Note: Symphony Mobile Bridge 2.6.0.4 does not support Windows XP or Windows Server 2003.

Mobile Bridge

Fixes	
VMS-1448	The iOS Mobile Application plays sound for push notifications.
VMS-1459	The SSL certificate that the Mobile Bridge creates during installation is exportable.

Release 2.6.0.3

Note: To install Symphony Mobile Bridge 2.6.0.3 on an Aimetis Physical Security Appliance, the Physical Security Appliance must have at least 16GB of storage for the operating system (SATA DOM).

Note: Symphony Mobile Bridge 2.6.0.3 does not support Windows XP or Windows Server 2003.

Mobile Bridge

Fixes	
VMS-1414	Mobile Bridge does not stop responding due to an unhandled exception.
VMS-1418	Mobile Bridge does not create duplicate log files.

Release 2.6.0.2

Note: To install Symphony Mobile Bridge 2.6.0.2 on an Aimetis Physical Security Appliance, the Physical Security Appliance must have at least 16GB of storage for the operating system (SATA DOM).

Note: Symphony Mobile Bridge 2.6.0.2 does not support Windows XP or Windows Server 2003.

Mobile Bridge

Fixes	
VMS-1412	Mobile Bridge installation does not restart unnecessarily in certain configurations.
VMS-1413	Clean installation no longer halts due to account elevation issue.

Release 2.6.0.1

Note: To install Symphony Mobile Bridge 2.6.0.1 on an Aimetis Physical Security Appliance, the Physical Security Appliance must have at least 16GB of storage for the operating system (SATA DOM).

Note: Symphony Mobile Bridge 2.6.0.1 does not support Windows XP or Windows Server 2003.

Mobile Bridge

Improvements	
VMS-1335	Improved the Mobile Bridge Web service to better support the Aimetis Thin Client.
VMS-1385	During installation, Mobile Bridge automatically creates a self-signed certificate for SSL communication with mobile devices, if one does not already exist for the installation.

Fixes	
VMS-1373	Errors in logging processes do not interrupt the connection between Symphony and the Mobile Bridge.

Release 2.6

Mobile Bridge

Fixes	
VMS-1283	Connection to Mobile Bridge no longer terminates due to certain network events.
VMS-1291	Cameras do not need to be recording for live video to work as expected in the mobile clients.

Release 2.2.4

Mobile Bridge

Fixes	
VMS-1214 VMS-1260	Mobile Bridge can retrieve live images/video reliably.

Release 2.2.3

Mobile Bridge

Fixes	
VMS-1153	Video now plays via Mobile Bridge again! Requires Symphony 6.14.8.1.

Release 2.2.2

Mobile Bridge

New Features	
VMS-1125	User permission status verified for video export when connected through Thin Client.

Fixes	
VMS-1081	“Unknown connection error” issue with Android app resolved.
VMS-1088	Missing component in Mobile Bridge installation corrected.
VMS-1095	Axis 216 camera issue with live video on iOS resolved.

Release 2.2.1

Mobile Bridge

Improvements	
VMS-1080	Support for new Apple Push Services.
VMS-1083	Thin Client time synchronized with Symphony Server if using Mobile Bridge.

Fixes	
VMS-1067	Mobile Bridge correctly runs the setup.exe file extracted in %temp% folder.

iOS – November 9, 2015

New Features	
VMS-1020	iOS client can open automatically when camera and preset ID sent from another mobile application.

Fixes	
VMS-1058	iOS mobile Symphony app continues working properly (while transmitting video) if username and password fields left empty.
VMS-1059	iOS mobile Symphony app continues working properly if Mobile Camera resolution changed in Symphony while mobile device is transmitting video.
VMS-1061	Video will stop transmitting when interrupted by low battery notification on iOS client.
VMS-1062	iOS mobile Symphony app working properly if video rotation changed in Symphony.
VMS-1068	iOS client compatible with older Mobile Bridge versions.
VMS-1069	Camera view works properly in iOS9.

Release 2.2

Known Issue:

IMPORTANT:

1. Due to an iOS app design requirement, the latest Mobile Bridge installer 2.2.0 will not install on Windows Server 2003 or Windows XP.
2. If you attempted to install Mobile Bridge 2.2.0 on your Windows Server 2003 or Windows XP machine and received an error message, your previous version of Mobile Bridge is still intact.
3. To be able to send videos from your mobile device to Symphony (new feature VMS-1025) in Mobile Client 2.2 or later, you will require Mobile Bridge 2.2 and it will need to be installed on a Windows 7 or later OS.

New Features	
VMS-1025	Support for video stream from iOS mobile device to Symphony. See KB article: How to set up Symphony for iOS mobile device camera transmission

Fixes	
VMS-697	Swedish translation corrected.
VMS-847	iOS8: User name properly displayed in acknowledge alarm screen.
VMS-887	Interface labels in iOS mobile aligned properly.
VMS-964	Copyright notice added to About section.
VMS-992	Mobile Bridge correctly adjusts for daylight savings time.
VMS-1016	H264 video working successfully in Android.
VMS-1021	Active Directory password correctly hidden (displayed as hash symbol) in Mobile Bridge logs.